TESTPASSPORT

練 習 問 題



高 品 質 な 学 習 リ ソ ー ス

https://www.testpassport.jp


1年間無料アップデート

Exam : **D-PE-OE-23**

Title : Dell Technologies PowerEdge Operate 2023

Version : DEMO

1.A technician wants to remotely log in to a server but finds that the IDRAC virtual Console feature Is not available. Use the simulator to explore the system.
What Is the cause of this Issue? Note: It is necessary to dose (x) the simulator window before you can select a response to this question.



A. The Virtual Console is disabled
B. Operating system not installed on remote server
C. The server has been powered down
D. There are more than the maximum number of active sessions
Answer: C

2.What is a requirement to operate GPUs in a Dell EMC PowerEdge R740 server?
A. All GPU cards must be installed at the same time
B. All GPU cards must be of the same type but can be a different model
C. All GPU cards must be of the same type and model
D. All GPU cards must be installed on the same riser card
Answer: C

3.What happens when the Hardware Root of Trust fails to validate the BIOS?
A. Boot Guard switches over to the backup BIOS and logs a warning in the system event log.
B. Automated BIOS Recovery process recovers the BIOS from the DUP saved in the control panel.
C. The server continues running and logs a critical error in the system event log.
D. The server shuts down and logs a critical error in the system event log.
Answer: D

4.A technician receives a new server with five drives.
They need to configure the drives based on the following requirements received from the administrator:
- Drive 0 as a single disk with no RAID
- Drives 1-3 as a RAID 5 with drive 4 as a hot spare just for this newly created RAID 5
The administrator plans to add more disks as separate RAID arrays at a later date but only wants drive 4 to be available for this first RAID 5 set.
How should the technician configure the drives?
A. Set drive 0 to Ready; set drives 1-3 as RAID 5; set drive 4 as a Global Hot Spare
B. Set drive 0 to Non-Raid; set drives 1-3 as RAID 5; set drive 4 as a Dedicated Hot Spare
C. Set drive 0 to Non-Raid; set drives 1-3 as RAID 5; set drive 4 as a Global Hot Spare
D. Set drive 0 to Ready; set drives 1-3 as RAID 5; set drive 4 as a Dedicated Hot Spare
Answer: B

5.A technician must update the firmware on a savor, but has no network connectivity.
What can the technician use to update the BIOS and iDRAC/ lifecycle Controller firmware?
A. OpenManage Server administrator DVD
B. ftp dell.com
C. NFS share
D. USB key with Dell Update Package
Answer: A